

QUARANTINE TECHNICAL SUPPLEMENT

Quarantine is a high end product and because of this it requires a lot of your system

QUARANTINE REQUIRES

386+, 530k free base memory and 4 meg XMS memory.

It is the XMS memory that is most important. Quarantine does not work with EMS.

DO NOT run EMM386 with Quarantine.

DO NOT run SMARTDRIVE with Quarantine.

DO NOT run ANY memory manager with Quarantine except HIMEM.SYS

To get Quarantine running, the best way, is to make a boot disk and experiment on that rather than your hard drive. To do this take a formatted disk and from the C: prompt type SYS A: This will copy the system files over. Now copy over your AUTOEXEC.BAT & CONFIG.SYS files. Leave this disk in your A: Floppy drive when you boot up and it will use that setup rather than your regular one.

Here is an example CONFIG.SYS and AUTOEXEC.BAT that will work well with Quarantine.

CONFIG.SYS

DEVICE=C:\DOS\HIMEM.SYS

DOS=HIGH

STACKS=9,256

DO NOT INCLUDE ANY LINES FOR BUFFERS OR FILES (eg. BUFFERS = 20)

CD USERS INSERT YOUR CD DRIVERS HERE

THIS IS JUST AN EXAMPLE YOUR WILL BE DIFFERENT

DEVICEHIGH=C:\SBPRO\DRV\SBPCD.SYS/D:MSCD001/P:220

Please note CD users that the path where your CD drivers are will vary hugely, so you should copy what is in your existing config.sys. The example given is merely an example.

AUTOEXEC.BAT

PATH C:\<Insert your path from your original system here>

SET BLASTER=A220 I7 D1 T4 REM ****This driver will vary from system to system

ALSO INSERT ANY OTHER SOUND DRIVERS HERE

C:\DOS\MSCDX.EXE/V/D:MSCD001/M:15REM OR WHATEVER YOUR CD DRIVER LINE IS

By using these configurations you should be able to run Quarantine with no problems. 90% of all running problems are caused by people running EMM386 or SMARTDRIVE. You should remove these and any other TSR's to run Quarantine. These TSR's cause messages such as DIVIDE OVERFLOW or STACK NOT FOUND. Do NOT PANIC the product is not damaged you just need to get rid of these programs.

CD USERS - If you select the FULL INSTALL option at any time during the game you can put in your own music CD and listen to your own music! Just pop it in and press C to change tracks!

CD VIDEO - To play with the video on CD requires a VERY high end graphics card. If you run the program and the video corrupts or jitters, your card does not support it. Run the game by typing "Q" instead.

If all else fails call us here at Gametek on 01753 553445 and we will give you free technical support.